


School of Computer Science & Engineering

**COMP9242 Advanced Operating Systems** 

2019 T2 Week 04b **Measuring and Analysing Performance** @GernotHeiser



# **Copyright Notice**

### These slides are distributed under the Creative Commons Attribution 3.0 License

You are free:

- to share—to copy, distribute and transmit the work
- to remix—to adapt the work

under the following conditions:

• Attribution: You must attribute the work (but not in any way that suggests that the author endorses you or your use of the work) as follows:

"Courtesy of Gernot Heiser, UNSW Sydney"

The complete license text can be found at http://creativecommons.org/licenses/by/3.0/legalcode



### **Performance Considerations**

#### What is performance?

- Is there an absolute measure
- Is there a baseline for relative comparison?

#### What are we comparing?

- Best case? Nice, but useful?
- Average case? What defines "average"?
- Expected case? What defines it?
- Worst case? Is it really "worst" or just "bad"?

Configuration matters:

- Hot cache easy to do – or cold cache?
- What is most relevant for the purpose?



# Benchmarking





# Lies, Damned Lies, Benchmarks

#### **Considerations:**

- Micro- vs macro-benchmarks
- Benchmark suites, use of subsets
- Completeness of results
- Significance of results
- Baseline for comparison
- Benchmarking ethics
- What is good? Analysing the results



# Benchmarking in Research & Development

#### Must satisfy two criteria:

- Conservative: no significant degradation due to your work
- *Progressive*: actual performance improvement in important cases
  - only needed if you work is actually about improving performance

#### Must analyse and explain results!

- Discuss model of system
- Present hypothesis of behaviour
- Results must test and confirm hypothesis

**Objectivity and fairness:** 

- Appropriate baseline
- Fairly evaluate alternatives



### Micro- vs Macro-Benchmarks

#### Microbenchmark

• Exercise particular operation

Micro-BMs are an analysis, not an assessment tool!

• drill down on performance

#### Macrobenchmark

- Use realistic workload
- Aim to represent real-system perf

### Benchmarking crime: Using micro-benchmarks only




### Standard vs Ad-Hoc Benchmarks

- Standard benchmarks are designed by experts
  - Representative workloads, reproducible and comparable results
  - Use them whenever possible!
  - Examples: SPEC, EEMBC, YCSB,...
- Only use ad-hoc benchmarks when you have no choice
  - no suitable standard
  - limitations of experimental system

Ad-hoc benchmarks reduce reducibility and generality, need strong justification!



### Obtaining an Overall Score for a BM Suite



### **Benchmark Suite Abuse**

"We evaluate performance using SPEC CPU2000. Fig 5 shows typical results." Subsetting introduces bias, makes score meaningless!


Benchmarking crime: Using a subset of a suite

Sometimes unavoidable (incomplete system) – treat with care, and justify well!

Results will have limited validity



### **Beware Partial Data**



### **Benchmarking crime**: Throughput degradation = overhead!



# Profiling

11 COMP9242 2019T2 W04 Performance

© Gernot Heiser 2019 – CC Attribution License



# Profiling

- Run time collection of execution statistics
  - invasive (requires some degree of instrumentation)
  - therefore affects the execution it's trying to analyse
  - good profiling approaches minimise this interference

Avoid with HW debuggers, cycleaccurate simulators

Identify targets for performance tuning – complementary to microbenchmarks

gprof:

- compiles tracing code into program
- uses statistical sampling with postexecution analysis



### Example gprof output

Each sample counts as 0.01 seconds.

% C	umulative	self		self	total	
time	seconds	seconds	calls	ms/call	ms/call	name
33.34	0.02	0.02	7208	0.00	0.00	open
16.67	0.03	0.01	244	0.04	0.12	offtime
16.67	0.04	0.01	8	1.25	1.25	memccpy
16.67	0.05	0.01	7	1.43	1.43	write
16.67	0.06	0.01				mcount
0.00	0.06	0.00	236	0.00	0.00	tzset
0.00	0.06	0.00	192	0.00	0.00	tolower
0.00	0.06	0.00	47	0.00	0.00	strlen
0.00	0.06	0.00	45	0.00	0.00	strchr

Source: http://sourceware.org/binutils/docs-2.19/gprof



# Example gprof output

granu	larity:	each sam	ple hit cov	vers 2 byte	(s) for 20.00% of 0.05 seconds
index	% time	self	children	called	name
					<spontaneous></spontaneous>
[1]	100.0	0.00	0.05		start [1]
		0.00	0.05	1/1	main [2]
		0.00	0.00	1/2	on_exit [28]
		0.00	0.00	1/1	exit [59]
		0.00	0.05	1/1	start [1]
[2]	100.0	0.00	0.05	1	main [2]
		0.00	0.05	1/1	report [3]
		0.00	0.05	1/1	main [2]
[3]	100.0	0.00	0.05	1	report [3]
		0.00	0.03	8/8	timelocal [6]




## Performance Monitoring Unit (PMU)

- Collects certain *events* at run time
- Typically supports many events, small number of event counters
  - Events refer to hardware (micro-architectural) features
    - Typically relating to instruction pipeline or memory hierarchy
    - Dozens or hundreds
- Counter can be bound to a particular event
  - via some configuration register, typically 2-4
- Counters can trigger exception on exceeding threshold
- OS can sample counters

Linux PMU interface: **oprof** Can profile kernel and userland







### Example oprof Output

#### \$ opreport

CPU: PIII, speed 863.195 MHz (estimated)

Counted CPU CLK UNHALTED events (clocks processor is not halted) with a ...

#### 506605 54.0125 cc1plus

450385 88.9026 cc1plus • • Drilldown of top 28201 5.5667 libc-2.3.2.so 27194 5.3679 vmlinux 677 0.1336 uhci\_hcd ... 163209 17.4008 lyx 60213 36.8932 lyx 23881 14.6322 libc-2.3.2.so 21968 13.4600 libstdc++.so.5.0.1 13676 8.3794 libpthread-0.10.so

17 COMP9242 2019T2 W04 Performance



### PMU Event Examples: ARM11 (Armv6)

Ev #	Definition	Ev #	Definition	Ev #	Definition
0x00	I-cache miss	0x0b	D-cache miss	0x22	
0x01	Instr. buffer stall	0x0c	D-cache writeback	0x23	Funct. call
0x02	Data depend. stall	0x0d	PC changed by SW	0x24	Funct. return
0x03	Instr. micro-TLB miss	0x0f	Main TLB miss	0x25	Funct. ret. predict
0x04	Data micro-TLB miss	0x10	Ext data access	0x26	Funct. ret. mispred
0x05	Branch executed	0x11	Load-store unit stall	0x30	
0x06	Branch mispredicted	0x12	Write-buffer drained	0x38	
0x07	Instr executed	0x13	Cycles FIRQ disabled	0xff	Cycle counter
0x09	D-cache acc cachable	0x14	Cycles IRQ disabled		
0x0a	D-cache access any	0x20			Developer's best friend!



# **Performance Analysis**



## Significance of Measurements

- Standard approach: repeat & collect stats
- Computer systems are high deterministic
  - Typically variances are tiny, except across WAN

All measurements are subject to random errors

Watch for divergence from this hypothesis, could indicate *hidden parameters!* 

### **Benchmarking crime**: No indication of significance of data!

Always show standard deviations, or clearly state they are tiny!



# How to Measure and Compare Performance

#### **Bare-minimum statistics:**

- At least report the mean ( $\mu$ ) and standard deviation ( $\sigma$ )
  - Don't believe any effect that is less than a standard deviation
    - 10.2±1.5 is not significantly different from 11.5
  - Be highly suspicious if it is less than two standard deviations
    - 10.2±0.8 may not be different from 11.5

For systems work, must be very suspicious if  $\sigma$  is *not* small!

Standard deviation is meaningless for small samples!

- Ok if effect  $\gg \sigma$
- use t-test if in doubt!




# Example from SPEC CPU2000

#### **Observations:**

22

- First iteration is special
- 20 Hz timer: accuracy 0.1 s!




Lesson: Need mental model of system, look for hidden parameters if model fails!



# How To Measure and Compare Performance

#### Noisy data:

- Eliminate sources of noise, re-run from same initial state
  - single-user mode
  - dedicated network
- Not always possible, may have to live with noise
- Possible ways out:
  - ignore highest & lowest values
  - take floor of data
    - maybe minimum is what matters





# How To Measure and Compare Performance

#### Vary inputs, check outputs!

- Vary data and addresses!
  - eg time-stamp or randomise inputs
  - · be careful with sequential patterns!
- Check outputs are correct
  - read back after writing and compare
- Complete checking infeasible?
  - do spot checks
  - run with checking on/off



**Beware optimisations!** 

- compilers eliminating code
- disks pre-fetching, de-duplicating

© Gernot Heiser 2019 – CC Attribution License



## **Real-World Example**

#### Benchmark:

• 300.twolf from SPEC CPU2000 suite


### Platform:

- Dell Latitude D600
  - Pentium M @ 1.8GHz
  - 32KiB L1 cache, 8-way
  - 1MiB L2 cache, 8-way
  - DDR memory @ effective 266MHz
- Linux kernel version 2.6.24

### Methodology:

• Multiple identical runs for statistics...





#### COMP9242 2019T2 W04 Performance

26



# A Few More Performance Evaluation Rules

- Vary one parameter at a time
- Record all configurations
- Measure as directly as possible
- Avoid incorrect conclusions from pathological data
  - sequential vs random access may mess with prefetching
  - 2<sup>n</sup> vs 2<sup>n</sup>-1, 2<sup>n</sup>+1 sizes may mess with caching

What is pathological depends a lot on circumstances!



### Most Important: Use a Model/Hypothesis


#### Model of the system that says how the system should behave

- Benchmarking should aim to support or disprove that model
- Need to think about this in selecting data, evaluating results, e.g.
  - I/O performance dependent on FS layout, caching in controller...
  - Cache sizes (HW & SW caches)
  - Buffer sizes vs cache size

Always check your system behaves according to the model!




### Example: Memory Copy






# Loop and Timing Overhead


- Ensure measurement overhead does not affect results!
- Eliminate by measuring in tight loop, subtract timer cost











**Benchmarking crime**: Selective data set hiding deficiencies!



### **Benchmarking Ethics**

#### **Comparisons with prior work**

- Sensible and necessary, but must be fair!
  - Comparable setup/equipment
  - Prior work might have different focus, must understand & acknowledge
    - eg they optimised for multicore scalability, you for mobile-system energy
  - Ensure you choose appropriate configuration
  - Make sure you understand what's going on!

### **Benchmarking crime**: Unfair benchmarking of competitor!



# Other Ways of Cheating with Benchmarks

- Benchmark-specific optimisations
  - Recognise particular benchmark, insert BM-specific optimised code
  - Popular with compiler-writers
  - Pioneered for smartphone performance by Samsung <u>http://bgr.com/2014/03/05/samsung-benchmark-cheating-ends</u>
- Benchmarking simulated system
  - ... with simulation simplifications matching model assumptions
- Uniprocessor benchmarks to "measure" multicore scalability
  - ... by running multiple copies of benchmark on different cores
- CPU-intensive benchmark to "measure" networking performance

### These are simply lies, and I've seen them all!



# **Understanding Performance**



# What is "Good" Performance?

- Easy if improving recognised state of the art
  - E.g. improving best Linux performance (where optimised)
- Harder if no established best-of-class baseline:
  - Evaluate best-of-breed system yourself -
  - Establish performance limits
    - Theoretical optimal scenario
    - Hardware-imposed performance limits


Remember: progressive and conservative criterion!

Remember: BM ethics!

© Gernot Heiser 2019 – CC Attribution License

Most elegant, but hardest!

# Real-World Example: Virtualisation Overhead



• virt.: 4 mode switches, 2 context switches, 3 × save+restore state



### Performance Counters Are Your Friends!

Counter	Native	Virtualized	Difference
Branch miss-pred	1	1	0
D-cache miss	0	0	0
I-cache miss	0	1	1
D-µTLB miss	0	0	0
I-µTLB miss	0	0	0
Main-TLB miss	0	0	0
Instructions	30	125	95
D-stall cycles	0	27	27
I-stall cycles	0	45	45 🖕
Total Cycles	93	292	199 •



### More of the Same

First step:	Ве	nchma	rk	Native	Virtualize	d	
improve	Со	Context switch [1/s]		615,046	444,50	)4	
representation!	Cre	Create/close [µs]		11		15	
	Su	Suspend [10ns]		81	15	54	
Second step: overheads in appropriate units!						guest dis-	alysis shows & enables 2 times!
Benchmark	Native	Virt.	Diff [µs]	Diff [cy]	# sysc	Cy/sysc 🤇	
Context switch [µs]	1.63	2.25	0.62	230	1	230	
Create/close [µs]	11	15	4	1472	2	736	
Suspend [µs]	0.81	1.54	0.73	269	1	269	



### And Another One...

Good or bad?

Benchmark	Native [µs]	Virt. [µs]	Overhead	Per tick
TDes16_Num0	1.2900	1.2936	0.28%	2.8 µs
TDes16_RadixHex1	0.7110	0.7129	0.27%	2.7 µs
TDes16_RadixDecimal2	1.2338	1.2373	0.28%	2.8 µs
TDes16_Num_RadixOctal3	0.6306	0.6324	0.28%	2.8 µs
TDes16_Num_RadixBinary4	1.0088	1.0116	0.27%	2.7 µs
TDesC16_Compare5	0.9621	0.9647	0.27%	2.7 µs
TDesC16_CompareF7	1.9392	1.9444	0.27%	2.7 µs
TdesC16_MatchF9	1.1060	1.1090	0.27%	2.7 µs

Timer interrupt virtualization overhead!



### Lessons Learned

- Ensure stable results
  - Get small variances, investigate if they are not
- Have a model of what to expect
  - Investigate if behaviour is different
  - Unexplained effects are likely to indications of problems don't ignore!
- Tools are your friends
  - Performance counters
  - Simulators
  - Traces
  - Spreadsheets

Annotated list of benchmarking crimes: http://gernot-heiser.org/benchmarking-crimes.html

